## Windows 10 Home to Education Upgrade

## https://kb.wisc.edu/images/group7/37387/Installation\_Guide.pdf

- 1. Go to software.wisc.edu
- 2. Sign in with your NetID
- 3. Click "Microsoft for Personally-owned Computers"
- 4. Scroll down to Downloads and click the "Windows 10 Education for students" link

Please enter	our email address before downloadi	ing software: bbadger@wisc.edu	
Microsoft	oftware for Personally-owned	d Computers	
A Windows -	Microsoft Windows 10 Education for st	tudents. 32- and 64-bit installers included. No charge for	
students! Mor Checksum (Sł	Info Read/Print End User License Agreement A256): b0aac9fb3cd298b55f941382fc3	3f68c4c358f8cedd766c95263fa72eea60faa0	
on't see what v	uu're looking for? Try the DolT Tech Sto	ore or WISC Software	

Note: If you don't see this Windows link, you have already used your one-time download for Windows 10 Education.

5. This will take about **30 minutes** to get the confirmation email which will look like this:



- 6. Once you get the email, click on the Windows icon on the bottom left and type "Settings"
- 7. In the search bar, type "Activation"

Update & Security		Activation	Windows is activated with a digital license					
C	Windows Update		Learn more					
•	Windows Security	Update pi To use a diffe	r <b>oduct key</b> erent product key on this device, select change					
₹	Backup	product key.						
Ø	Troubleshoot	🔍 Change product key						
3	Recovery	Add a Mie	crosoft account					
$\oslash$	Activation	Your Microso	oft account unlocks benefits that make your					
ቆ	Find my device	experience w reactivate W Learn more	indows 10 on this device.					
Ĩŧ	For developers	🕂 Add an	account					

8. Click change product key and enter 25 character key from email from wiscorder@doit.wisc.edu

Enter a product key		
Enter a product key		
Your product key should be in an email from whoever sold or distr or on the box the Windows DVD or USB came in.	ibuted Window	s to you,
Product key		
XXXXX-XXXXX-XXXXX-XXXXX		
	Next	Cancel

9. Follow the prompts to finish activating windows. It may take a while with a few restarts depending on your version of Windows 10. You should receive this message once complete:

Windows is activated	
Windows is activated We've activated this copy of Windows.	
	Close

10. To double check you have Windows 10 Education, go back to the Activation screen which should display the Edition on the top of the page.

← Settings	– 🗆 ×						
命 Home	Activation						
Find a setting	Windows Edition Windows 10 Education						
Update & Security	Activation Windows is activated with a digital license						
$\bigcirc$ Windows Update	Learn more						
Windows Security	Update product key To use a different product key on this device, select change						
↑ Backup	product key.						
P Troubleshoot	🔍 Change product key						
S Recovery	Where's my product key?						
	Depending on how one Windows, activation will use a divital						

11. Bitlocker encryption is necessary for UW Health remote access. To enable BitLocker, click the Windows icon and search "Bitlocker"

1	2	
	1	
_	-	٠

itLocker Drive Encryption			- 0	×
$ ightarrow$ $\land$ $\uparrow$ 🍖 $ ightarrow$ Control	I Panel > All Control Panel Items > BitLocker Drive Encryption	√ Ö	Search Control Panel	P
Control Panel Home	BitLocker Drive Encryption Help protect your files and folders from unauthorized access by protecting your drives with BitLocker.			
	Operating system drive			
	C: BitLocker off		$\bigcirc$	
	S Turn on BitLocker			
	Fixed data drives			
	Removable data drives - BitLocker To Go			
	ESD-USB (D:) BitLocker off		$\odot$	
ee also				
PM Administration				
isk Management				

13. Click "Turn on BitLocker" and follow the on-screen prompts. It will require you to click "Next" a few times until you decide how to back up your recovery key. Bitlocker creates a key to store in a secondary location for security reasons. Here, you will want to click "Save to a file" and save it to either print it out, save to a flash drive, Google Drive, or Box. For extra redundancy after saving it, you can take a picture of the open document with your phone to have it more easily accessible to you. If you lose the Bitlocker key, there is no way to recover it.

	×	9	🤾 Save BitLocker red	covery k	cey as				×
←	RitLocker Drive Encryption (C:)		← → • ↑ 💆	⇒ ESE	D-USB (D:)	√ Č	Search ESD-USB	(D:)	Q
	How do you want to back up your recovery key?		Organize 🔻 🛛 Ne	ew folde	er				0
			🖊 Downloads	* ^	Name	D	ate modified	Туре	
	Some settings are managed by your system administrator.		🔮 Documents	*	boot	1	1/2/2018 11:33 AM	File folder	
	A recovery key can be used to access your files and folders if you're having problems unlocking your PC. It's a good idea to have more than one and keep each in a safe place other than your PC.		Pictures	*	efi	1	1/2/2018 11:33 AM	File folder	
	······································		CAPTURES		sources	1	1/2/2018 11:33 AM	File folder	
			👌 Music		support	1	1/2/2018 11:47 AM	File folder	
	→ Save to your <u>M</u> icrosoft account		📑 Videos						
	$\rightarrow$ Save to a file	>	a OneDrive						
	$\rightarrow$ <u>P</u> rint the recovery key	>	💻 This PC						
		>	🖆 ESD-USB (D:)						
			a	~	<				>
			File name:	BitLoc	cker Recovery Key C5XXY20A-E23D-	40DB-AB5F-1836C	D03C562		~
	How can I find my recovery key later?		Save as type:	Text Fi	iles (*.txt)				~
	Next Cancel		<ul> <li>Hide Folders</li> </ul>				Save	Cancel	
							ſ		1

BitLocker Recovery Key CXXY720A-E23D-40DB-AB5F-1836CD03C562 - Notepad	_		×
File Edit Format View Help			
BitLocker Drive Encryption recovery key			~
To verify that this is the correct recovery key, compare the start of the following identifier with the ident:	ifier	value	di
Identifier:			
CXXY720A-E23D-40DB-AB5F-1836CD03C562			
If the above identifier matches the one displayed by your PC, then use the following key to unlock your drive			
Recovery Key:			
717376-709875-154550-167849-592793-405988-366903-041657			
If the above identifier doesn't match the one displayed by your PC, then this isn't the right key to unlock yo Try another recovery key, or refer to https://go.microsoft.com/fwlink/?LinkID=260589 for additional assistance	our dr ≥.	ive.	

## Once saved, follow the defaults on the next two pages (shown below).

14. Check the Run BitLocker system check and then click continue.



It will prompt you to restart the computer to start the encryption process. After restarting, log in and there will be a progress bar in the bottom right toolbar to monitor the progress. You can use the computer in the meantime as this encrypts in the background.